

KB Article 2013_EE_770
March 07, 2013
Last update: April 02, 2013

How Backup Manager in Cellica Database application Works?
 (Personal/Enterprise Edition)

Product(s)

Cellica Database (Wi-Fi, Internet and Anywhere) Personal Edition or Enterprise Edition

Symptoms

Not Applicable.

Details:

Backup Manager is a tool to view or store old copies of updated data from a device or the desktop. It can be immensely useful in events such as if same record is updated from desktop and device, In such a case device side record get overwrite by the desktop version of the record, but you can get the copy of device version of a record in Backup Manager.

Following are the different scenarios which explain how records move from the original table and Backup Manager Module.

Operations on Device Side:

Device Side Operations	Changes In Backup Of Device Side	Removal Of a Record From Backup Manager
Add Record	Record Added In Backup Manager	On Successful Sync
Update Record	Record Added In Backup Manager	On Successful Sync
Delete Record	No Changes in Backup Manager	No Changes in Backup Manager


Operations on Desktop Side:

Desktop Side Operations	Changes In Backup Manager Of Device Side	Removal Of Record From Backup Manager
Add Record	No Changes in Backup Manager	No Changes in Backup Manager
Update Record	No Changes in Backup Manager	No Changes in Backup Manager
Delete Record	If the record is updated at device side, device copy of record will be added in Backup Manager.	Manually remove the record from Backup Manager at device side
Profile Delete	If Backup Manager contains records for this profile, those records will not be removed from Backup Manager automatically on syncing. Only profile will get removed, and Backup will be preserved which contains work from device side for this profile which is not synced with	1) Manually remove Record from Backup Manager. OR 2) Manually remove Backup Profile from Backup Manager.

desktop.

Manually Removing Records from Backup Manager:

You can manually remove records in Backup Profile in Backup Manager by,
**Tap “More Options” (...) On Home Screen => Tap Backup Manager => Tap Backup Profile to open
 => Double tap on Record => Opens Record View => Tap “Delete” Icon Present At Top Right Corner
 Of Record View.**



Manually Removing Backup Profile from Backup Manager:

You can manually remove Backup Profile in Backup Manager by,
**Tap “More Options” (...) On Home Screen => Tap Backup Manager => Tap Backup Profile to open
=> Tap More Options (...) => Tap “Delete Table” from Options.**

